



Release Notes

www.Micrium.com

Revision History

Version	Date	Description
V1.26	2010 Apr	Improvements
V1.25.01	2010 Apr	Port updates ONLY — NO changes to core files
V1.25	2010 Jan	Bug fixes & improvements
V1.24	2009 Dec	New features, bug fixes, & improvements
V1.23	2009 Jul	CPU timestamp, timer, & time measurement features
		First version with release history & user's manual

New Features

Version 1.26

N/A

Version 1.25.01

N/A

Version 1.25

N/A

Version 1.24

V1.24-001

Added CPU_STK_SIZE data type definition to each cpu.h.

V1.24-002a

Added (optional) CPU timestamp's timer frequency, 'CPU_TS_TmrFreq_Hz'.

V1.24-002b

Added new CPU timestamp timer functions:

```
CPU_TS_TmrFreqGet() gets the CPU timestamp's timer frequency sets the CPU timestamp's timer frequency (in Hertz)
```

See also 'New Features V1.23-001c'.

Version 1.23

V1.23-001

Added new CPU timestamp, timer, & time measurement features. [Note that an application MUST call <code>CPU_Init()</code> to initialize CPU timestamp **OR** time measurement features prior to any other calls to CPU time functions.]

V1.23-001a

Added CPU_CFG_TS_EN in cpu_cfg.h to enable/disable CPU timestamps:

```
gets the current, real-time value of 64-bit CPU timestamp, returned via two 32-bit values

CPU_TS_GetLo() gets only the lower 32-bits of 64-bit timestamp

CPU_TS_Update() updates the real-time value of 64-bit CPU timestamp (see 'New Features V1.23-001c

CPU_TS_TmrRd()')
```

See also 'Changes V1.25-001a1 & V1.25-001c'.

V1.23-001b

Added CPU_CFG_INT_DIS_MEAS_EN & CPU_CFG_INT_DIS_MEAS_OVRHD_NBR in cpu_cfg.h to enable/disable measuring interrupts disabled times :

See also 'Changes V1.25-002'.

V1.23-001c

The following timer functions **MUST** be implemented in an application if either CPU timestamps **OR** interrupts disabled time measurements are enabled:

```
CPU_TS_TmrInit() initializes & starts a hardware (or software) timer to update CPU timestamps & time measurements

CPU_TS_TmrRd() gets current hardware (or software) timer value to update CPU timestamps or time measurements

CPU_TS_to_uSec() convert (up to) 64 bits of a CPU timestamp value into microseconds, returned via two 32-bit values
```

See also 'Changes V1.25-001d & V1.25-001e' & 'New Features V1.24-002b'.

Improvements

Version 1.26

V1.26-001

Updated µC/CPU's MISRA-C compliance :

V1.26-001a

Added argument names to function pointer data types.

V1.26-001b

Encapsulated all macros defined as code blocks within do..while(0) conditions.

Version 1.25.01

N/A

Version 1.25

V1.25-001a

Improved CPU timestamp API & performance. See also 'Changes V1.25-001'.

V1.25-002a

Refactored CPU_CntLeadZeros() to improve performance.

V1.25-002b

Added 64-bit support to CPU_CntLeadZeros().

V1.25-003

Added 64-bit data types to most cpu.h's.

Version 1.24

V1.24-001

Updated uC/CPU's MISRA-C compliance :

V1.24-001a1

Appended unsigned 'u' qualifier to all unsigned integer constants.

V1.24-001a2

Removed redundant 'L' qualifier from all long integer constants.

V1.24-001b

Replaced all calls to unbounded $\mu C/LIB$ string library functions [e.g. Str_Copy()] with calls to bounded functions [e.g. Str_Copy_N()].

Version 1.23

V1.23-001

Added CPU_CFG_MODULE_PRESENT header guard to ensure cpu_cfg.h is processed only once, regardless if #include'd by multiple source or header files.

Changes

Version 1.26

N/A

Version 1.25.01

V1.25.01-001a

Renamed \Micrium\Software\uC-CPU\Win32\Microsoft directory to \Micrium\Software\uC-CPU\Win32\Visual Studio.

V1.25.01-001b

Refactored \Micrium\Software\uC-CPU\Win32\Visual Studio port files' critical section initialization & implementation.

Version 1.25

V1.25-001

Refactored CPU timestamps configuration, API, & implementation to improve performance (see also 'µC/CPU's User's Manual Section 3.03'):

V1.25-001a1

Replaced cpu_cfg.h configuration constant CPU_CFG_TS_EN with new configuration constants:

```
CPU_CFG_TS_32_EN enables 32-bit CPU timestamps enables 64-bit CPU timestamps
```

V1.25-001a2

Added cpu_cfg.h configuration constant CPU_CFG_TS_TMR_SIZE to configure the word size of the CPU timestamp's hardware (or software) timer.

V1.25-001b1

Replaced CPU_TS data type with new CPU timestamp data types:

CPU_TS32	handles 32-bit CPU timestamps
CPU TS64	handles 64-bit CPU timestamps

V1.25-001b2

Added CPU_TS_TMR data type to handle CPU timestamp timer values instead of CPU_TS.

V1.25-001c

Replaced CPU_TS_Get() & CPU_TS_GetLo() with new CPU timestamp functions:

```
CPU_TS_Get32() gets 32-bit CPU timestamp
CPU_TS_Get64() gets 64-bit CPU timestamp
```

V1.25-001d

Modified developer-defined CPU timestamp timer function prototypes:

V1.25-001e

Replaced (optional) developer-defined CPU_TS_to_uSec() with new CPU timestamp functions:

```
CPU_TS32_to_uSec() converts 32-bit CPU timestamp to microseconds CPU_TS64_to_uSec() converts 64-bit CPU timestamp to microseconds
```

V1.25-002

Modified CPU interrupts disabled time measurement function prototypes:

Version 1.24

N/A

Version 1.23

V1.23-001a

Moved CPU ERR data type definition from each cpu cfg.h to cpu core.h.

Corrections

Version 1.26

N/A

Version 1.25.01

N/A

Version 1.25

V1.25-001c

Previous CPU_TS_Get() failed to re-entrantly calculate the current CPU timestamp since the current CPU timestamp timer was read [via a call to CPU_TS_TmrRd()] with interrupts enabled but saved for the next timestamp calculation with interrupts disabled. Fixed in CPU_TS_Get32() & CPU_TS_Get64() [see 'Changes V1.25-001c'] by calling CPU_TS_TmrRd() with interrupts disabled.

Version 1.24

N/A

Version 1.23

N/A

Known Problems

Version 1.26

N/A

Version 1.25.01

N/A

Version 1.25

N/A

Version 1.24

N/A

Version 1.23

N/A

Limitations

001

Support for 64-bit data ${\bf NOT}$ available for some CPUs

Contacts

Micriµm

949 Crestview Circle Weston, FL 33327 USA

+1 954 217 2036

+1 954 217 2037 (FAX)

e-mail: <u>Licensing@Micrium.com</u> WEB: <u>www.Micrium.com</u>